



Education Software Installer 2013 December update

Mac OS X operating system software

Installation guide

SMART[®]

Trademark notice

SMART Notebook, SMART Ink, SMART Response, smarttech, the SMART logo and all SMART taglines are trademarks or registered trademarks of SMART Technologies ULC in the U.S. and/or other countries. Mac, OS X, Safari and Finder are trademarks of Apple Inc., registered in the U.S. and other countries. All other third-party product and company names may be trademarks of their respective owners.

Copyright notice

© 2013 SMART Technologies ULC. All rights reserved. No part of this publication may be reproduced, transmitted, transcribed, stored in a retrieval system or translated into any language in any form by any means without the prior written consent of SMART Technologies ULC. Information in this manual is subject to change without notice and does not represent a commitment on the part of SMART.

This product and/or use thereof covered by one or more of the following U.S. patents.

www.smarttech.com/patents

12/2013

Contents

Chapter 1: Getting started	1
Computer requirements	1
Deploying the software	2
Chapter 2: Installing the software	3
Starting the installer	3
Installing the software using the installer	4
Chapter 3: Removing the software	7

Chapter 1

Getting started

Computer requirements	1
Deploying the software	2

This guide explains how to install the following software using the Education Software Installer:

- SMART Notebook™ collaborative learning software 11.4
- 3D Tools for SMART Notebook software
- SMART Product Drivers 11.4
- SMART Ink™ 2.0
- SMART Response™ 2013 assessment software
- SMART Common Files

This guide is intended for teachers, IT administrators and others responsible for installing software on teachers' computers.

To use this guide, you must have access to the installation DVD or the Internet.

Computer requirements



NOTE

Operating systems and other third-party software released after this SMART software might not be supported.

Before you install the software, ensure your teachers' computers meet the minimum requirements:

- Intel® Core™ 2 Duo processor or better
- 2 GB of RAM

CHAPTER 1

Getting started

- Free hard disk space:

Software	Space required
SMART Notebook software	183 MB
Gallery Essentials	544 MB
Lesson Activity Toolkit	111 MB
3D Tools for SMART Notebook software	68 KB
SMART Product Drivers	190 MB
SMART Ink	9 MB
SMART Response software	181 MB
SMART Common Files	630 MB
Recommended total free hard disk space	1.9 GB

- Mac OS X 10.7, 10.8 or 10.9 (Mavericks) operating system software
- Adobe® Flash® Player 11.9 for SMART Notebook software
- Safari application program 5.1 or later
- Internet access to download SMART software

Deploying the software

If you're an IT administrator and you want to deploy the software to multiple computers, see the *Education Software Installer 2013 system administrator's guide* (smarttech.com/kb/170626).

Chapter 2

Installing the software

Starting the installer	3
Installing the software using the installer	4

Starting the installer

You can start the installer by inserting the DVD into the computer or by downloading the installer from the SMART website.

To start the installer from the DVD

1. Insert the DVD into the computer.

The *Education Software Installer* dialog box appears.



NOTE

If the dialog box doesn't appear, browse to and open **[DVD]/CDBrowser.app** using the Finder.

2. Click **Install**.

The installer appears.

To download and start the installer from the website

1. Go to smarttech.com/software, click the **Choose a version** button for the software you want to install, and then select the version of the software you want to install.
2. Click **Download**.
3. Select **Yes** if you have product keys for the software.

OR

Select **No** if you don't have product keys for the software and want to install a 30-day free trial.

4. Enter the requested information, and then click **Start Download**.
5. Save the file to a temporary location.

CHAPTER 2

Installing the software

6. Double-click the file.
The installer appears.

Installing the software using the installer

■ To install the software using the installer

1. Start the installer as described in the previous procedures.
2. Click **Continue**.
3. Read the software license agreement, and then click **Continue**.
4. If you accept the terms in the software license agreement, click **Agree**.
OR
If you don't accept the terms in the software license agreement, click **Disagree**.
5. Select the check box if you want to join the Customer Experience Program, and then click **Continue**.
6. Select the disk on which you want to install the software, and then click **Continue**.
7. Select the software you want to install.



NOTE

SMART Notebook and **SMART Product Drivers** are selected by default.

8. If you selected **SMART Notebook** in step 7, click its disclosure triangle, and then select the Gallery collections you want to install on to your computer.
9. If you selected **SMART Response** in step 7, click its disclosure triangle, and then select **Start Desktop Menu at log in** to start SMART Response software when you first log on to your computer.

CHAPTER 2

Installing the software

10. If you selected **SMART Product Drivers** in step 7, click its disclosure triangle, and then select the appropriate check boxes:

- **SMART Ink** to install SMART Ink



NOTE

If you selected **SMART Product Drivers** in step 7, the installer automatically selects **SMART Ink**.

- **Start SMART System Menu at log in** to start the SMART System Menu when you first log on to your computer
- **Make SMART Ink Document Viewer the default PDF viewer** to set the SMART Ink Document Viewer as the default program used to open PDF files.

11. Click **Continue**.

12. Click **Install**.

A dialog box appears, prompting you for your name and password.

13. Type your name and password, and then click **OK**.

The installer installs the software you selected in step 7.

Chapter 3

Removing the software

You can remove SMART software using SMART Uninstaller.

To remove SMART software

1. In Finder, browse to and double-click **Applications/SMART Technologies/SMART Uninstaller**.
2. Select the software you want to remove.



NOTES

- Some SMART software is dependent on other SMART software. For example, if you select **SMART Notebook**, SMART Uninstaller removes SMART Response software automatically because SMART Response software is dependent on SMART Notebook software.
- SMART Uninstaller automatically removes any supporting software that is no longer being used. If you choose to remove all SMART software, SMART Uninstaller automatically removes all supporting software, including itself.



TIPS

- To select more than one software application, hold down SHIFT or COMMAND while selecting the software applications.
- To select all software applications, press **Select All**.

3. Press **Remove**, and then press **OK**.
4. If prompted, enter a user name and password with administrator privileges, and then press **OK**. SMART Uninstaller removes the selected software.
5. Close SMART Uninstaller when done.

SMART Technologies

smarttech.com/support

smarttech.com/contactsupport

smarttech.com/kb/170628